PHOTOSHOP FILE SET UP INSTRUCTIONS FOR EPSON 3880

Prior to printing students must have:
- ATTENDED A PRINTING DEMO FROM YOUR INSTRUCTOR OR LAB ASSISTANT.
- DEPOSITED FUNDS INTO ART ACCOUNT THROUGH STUDENTS ACCOUNTS (3200 BLDG).

See course handouts and follow instructions from your instructor for course specific workflow instructions.

FILE SET UP: The following procedures must be completed prior to moving to the print stations.
- For best print results, edit RAW files in Lightroom or Camera Raw then save as TIFF OR PSD at full size.

1. Check Image Size and size to print:
IMAGE >IMAGE SIZE (COMMAND + OPTION + i)
Image size must fit within the paper size 8.5X11 OR 13X19
- if resizing image dimensions, leave Resample checked and adjust width or height RESOLUTION: 360 OR 300 PPI





-NOTE: THE NATIVE RESOLUTION OF YOUR CAMERA MAY BE DIFFERENT THAN THE ABOVE RESOLUTIONS.

This is fine for print but …
- if you chose to upsample (i.e. go from 240 to 360ppi)
UNCHECK Resample before changing resolution.

2. Soft Proofing
VIEW > PROOF SETUP > CUSTOM





Device to Simulate > select your paper



SOFT PROOFING — make any necessary exposure, contrast or color adjustments to your photo before printing.

3. FILE > PRINT (COMMAND+P)

SELECT PRINT SETTINGS



PHOTOSHOP FILE SET UP INSTRUCTIONS FOR EPSON 3880
See handouts and follow instructions for your course specific workflow instructions.

4. PRINTER SETTINGS

PLEASE DOUBLE CHECK YOUR SETTINGS ARE ALL CORRECT FOR THE PAPER AND PRINTER.

SELECT THE CORRECT PRINTER



Layout: choose image orientation

SELECT Print Settings



SELECT: Paper Size



US Letter (8.5x11in) or

Super A3 13 x 19 in

Choose Printer Settings from the dropdown menu



Paper Size
based on your choice of paper size

Media Type
based on your choice of paper type:
LUSTER:
Ultra Premium Photo Paper Luster
GLOSSY:
Premium Photo Paper Glossy

Output Resolution
SuperPhoto - 1440 dpi

CLICK : Save

16 BIT OUTPUT
ONLY IF YOUR PHOTO IS IN 16-BIT

PHOTOSHOP FILE SET UP INSTRUCTIONS FOR EPSON 3880
See handouts and follow instructions for your course specific workflow instructions.

4. PRINTER SETTINGS (continued)

ALWAYS DOUBLE CHECK SETTINGS PRIOR TO PRINTING



Color Handling:
Photoshop Manages Colors

Printer Profile:

ARISTA LUSTER:
Epson Stylus Pro 3880 PremiumLusterPhotoPaper
ARISTA GLOSSY:
Epson Stylus Pro 3880 PremiumGlossyPhotoPaper

Rendering Intent:
Relative Colorimetric or Perceptual

✔ Black Point Compensation

Load Paper: Shiny/Tacky Side UP

CLICK

REMEMBER

8.5" x 11" - $1.25 per sheet
13" x 19" - $5 per sheet

44" - $8 per linear foot

** No IOU'S — You only can print if you have sufficient funds in your print log. Deposit funds into ART account through the Student Accounts / Cashiers Office (3200 BLDG).

** Double check all of your settings and paper orientation prior to printing. Students are responsible for mistakes in the print workflow or loading paper incorrectly.

** FUNDS IN THE PRINT LOG DO NOT CARRY OVER SEMESTER TO SEMESTER.

** Please notify your instructor or lab technician if you run into any problems.